

Technical News Bulletin

May 6, 2008

MLP Plus - Five Fill-Point Capacity Measurements

Now available in MLP Plus Software revision 3.43 and higher, is the added feature to measure the capacity at up to five Fill-Point locations inside the bottle.

The Capacity Option on the MLP measures the volume of liquid a bottle can hold at a specific location down from the top of the bottle. Typically, only one measurement is made, however, at the request of our customers more than one measurement was needed, so we added the capability to measure five separate points.

Some users may select two Fill-Point locations: One at the actual product fill-point and one at the top of the bottle. This is referred to as Overflow Capacity.

Is there an application where five fill-points are required? Who knows! But we are prepared.

